

# TBB Scenario Create User manual

This document is a generic User Guide document for use by TBB Scenario Create Program It provides guidance and template material which is intended to assist users of how to import or create scenarios. And add commands to a project

## Installation:

The TBB app is a pre-installed software, so a double click on the TBB Scenario Create.jar file will launch the application main screen.

## How to use the TBB application:

The TBB Scenario Create program main screen allows you to chose from two main options


### 1- Import an existing scenario file:

Importing an existing scenario to the TBB Scenario Create program can be done easily by first clicking on import scenario button form the main screen



Then a new window will appear this window will allow you to choose the file form your computer.

Chose the appropriate scenario file




*Then click open which will load the scenario into the program*

## 2- Creating new Scenario

Creating a new scenario can be done by pressing on the new scenario button from the main screen of the TBB Scenario Create



Then it will open the create scenario screen which will allow the user to add command, remove command or to move commands



Adding command can be easily done choosing from the command drop-down menu

1-

The drop-down command menu that allow the user to choose from a list of commands which are (Read text, pause, Display text, Start Repeat, End Repeat, skip button, User input, sound, reset buttons, clear all cell Display, clear cell Display, Display cell pins, Display Character, Raise pin, Lower pins, Skip location)

Then pressing on add command button, a message will pop up to add the command arguments. Adding the correct arguments to the command then pressing ok button it will appear on the command list

There is two ways you can add sound to the scenario

- Import an audio file from the computer
- record sound from the sound window that will pop up

Sound Selection



The image shows a 'Sound Selection' dialog box with a close button (X) in the top right corner. Inside the dialog, there is a green square icon with a white question mark. To the right of the icon, the text 'File Chosen' is displayed in bold, followed by 'N/A' in blue. Below this, there is a large blue button labeled 'Choose existing sound file'. Underneath the button is the text '--- OR ---'. Below that is a text input field labeled 'File name...'. Below the input field is a large blue button labeled 'Start Recording'. Below the 'Start Recording' button is a large grey button labeled 'Stop Recording'. At the bottom center of the dialog is a small blue button labeled 'OK'.

2-

the command list is where all added commands is displayed. select any command and then press action buttons like Remove, move up and move down you can edit the command location or remove the command.

Export the scenario to a text file to be used in the braille device is can be done by the Export Scenario button. Then a new window will appear this window will allow you to choose where you want to save the scenario file in your computer.

S

